

artisJet proV6 - USER MANUAL FOR MAC PRODUCTS

OPENING THE PRINT SOFTWARE

1. Open the **Print Software (artisJet Workflow Station for proV6)** by double clicking on the software icon located on the desktop.



2. Within the Print Software, double click on the **“New Job”** icon located on the left top corner of the screen. This will open the **Design Software (artisRIP V9.0)**.




CHOOSING THE PRODUCT DESIGN


3.1. After the Design Software (artisRIP V9.0) window is open, go to **“File”** tab located at the left top of the screen, click on it and select **“Open”**. Open the product frame (template preset) you want to print (read step 3.2).




3.2. A new window will be displayed. Locate the **“PRODUCTS”** folder and select the product frame (template preset) for **“Bullet-LIPS.tpf”**. Click the **“Open”** button.




4. The product frame is now opened. Click once on the design text (example: “Lily”) to select it. While the text is highlighted, right click and select **“Artistic text”** to change the name.





5.1. To change the artwork / emoji (example: “”), click once on the artwork to highlight it. Then go to the “File” tab located at the left top corner of the screen, and select “Import Picture...”.



5.2. The “Import Graph File” window is now opened. Look in the emojis / artwork folder (example: “MAC Emojis” folder) and select the preferred emoji. Click the “Open” button.




5.3. The “” emoji will be replaced with the new emoji (example: “”). The “Import Picture” small window will appear. Choose “To Selected Frame” and click the “OK” button to finalize the replacement of the emoji. Your design is ready for print.




PRINTING THE PRODUCT


6.1. In the Design Software (artisRIP V9.0), click the 5th function button to print.



6.2. The “Print” window will open, showing the print progress of the file.




7. Place the product on the printing template / jig.



8. Make sure to close the cover of the printer.



9. On the Control Panel of the artisJet proV6 printer, click the “ENTER” button located in the middle. The “Printer ready” message will be displayed on the Control Panel screen.



10. From the Print Software (artisJet Workflow Station for proV6) click on the “Print” icon.



11. The printer starts to print and the “Printing” message is displayed on the Control Panel screen.



12. When the printing finishes, the “Printing complete” message will be displayed on the Control Panel screen.



13. Enjoy the printed product.

